




X-Lite 4 for Mac

User Guide

CounterPath Corporation
Suite 300, One Bentall Centre
505 Burrard Street, Box 95
Vancouver, BC V7X 1M3
Tel: 604.320.3344
sales@counterpath.com www.counterpath.com

© August 2011 CounterPath Corporation. All rights reserved.

This document contains information proprietary to CounterPath Corporation, and shall not be used for engineering, design, procurement, or manufacture, in whole or in part, without the consent of CounterPath Corporation. The content of this publication is intended to demonstrate typical uses and capabilities of the CounterPath X-Lite 4 *for Mac* softphone application from CounterPath Corporation. Users of this material must determine for themselves whether the information contained herein applies to a particular IP-based networking system. CounterPath makes no warranty regarding the content of this document, including—but not limited to—implied warranties of fitness for any particular purpose. In no case will CounterPath or persons involved in the production of this documented material be liable for any incidental, indirect or otherwise consequential damage or loss that may result after the use of this publication.

CounterPath and the  logo are trademarks of CounterPath Corporation.

Mac, Mac OS, QuickTime and iSight are registered trademarks of Apple Inc., registered in the U.S. and other countries

This manual corresponds to X-Lite 4 *for Mac* version 4.1.

Revision 2

Contents

Introduction.....	1
Installation and Setup.....	3
Getting Ready	3
Configuring X-Lite 4	4
Troubleshooting	5
Checking for X-Lite 4 Updates.....	5
Using X-Lite 4	7
The Onscreen Softphone.....	7
Placing a Call	9
Handling an Incoming Call.....	11
Handling an Established Call.....	12
Handling Video Calls.....	13
Voicemail.....	14
Instant Messaging	15
Using the Resources.....	17
Contacts Tab	17
History Tab	20
Sharing Online Status	21
Configuring X-Lite 4	25
Configuring your Account	25
General Preferences	34
A Troubleshooting	43
B Dial Plan.....	47
C Location of Data Files	51
D Glossary	52

1 Introduction

Standard Telephone Features

The CounterPath X-Lite 4 *for Mac* softphone has all standard telephone features, including:

- Call display and Message Waiting Indicator (MWI).
- Speakerphone and Mute.
- Redial, Hold.
- Call history – list of received, missed, and dialed calls.

Enhanced Features and Functions

X-Lite 4 also supports the following features and functions:

- Video
- IM and presence using the SIMPLE protocol.
- Managed contact list.
- Automatic detection and configuration of audio devices.
- Acoustic echo cancellation, automatic gain control, voice activity detection.
- Support for the following audio codecs:
DVI4, DVI4 Wideband, G.711aLaw, G.711uLaw, GSM, iLBC, L16 PCM Wideband, Speex, Speex FEC, Speex Wideband, Speex Wideband FEC.
- Support for the following video codecs:
H.263, H.263+ 1998.
- Automatic selection of the best codec based on the other party's capability, the available bandwidth, and network conditions. X-Lite 4 switches the codec within a call in response to changing network conditions.
- Compliance to 3261 SIP standard.
- STUN and ICE NAT traversal.
- Support for DTMF (RFC 2833, inband DTMF or SIP INFO messages).

2 Installation and Setup

2.1 Getting Ready

Account Information

After choosing a VoIP service provider, you will need the following information:

- User name and password
- Authorization Name (if applicable)
- Domain
- Firewall traversal and other network information; see “Configuring X-Lite 4” on page 25.

System Requirements

- Operating System: Mac OS 10.5 or above operating system software.
- Connection: IP network connection (broadband, LAN, wireless)

Multimedia Device Requirements

X-Lite 4 requires both speakers and a microphone to make calls. Any of the following configurations are acceptable:

- External speakers and microphone
- Built-in speakers and microphone
- Dual-jack multimedia headset
- USB multimedia headset
- USB phone.

X-Lite 4 is optimized to work with Apple iSight camera.

2.2 Configuring X-Lite 4

Setting up your Account

After obtaining SIP account information from your VoIP service provider, you can set up your X-Lite 4 account.

1. From the menu, choose X-Lite 4 Beta > Preferences. The Application - Preferences window appears.
2. Click on Accounts and complete the User Details area with the information obtained from your VoIP service provider.

The screenshot shows the 'Account' configuration dialog box in X-Lite 4. The 'Account' section at the top has 'Account name' set to 'Account 1', 'Protocol' set to 'SIP', and 'Use for' checked for 'Call' and 'IM/Presence'. Below this are tabs for 'General', 'Voicemail', 'Topology', 'Presence', 'Transport', and 'Advanced'. The 'User Details' section contains fields for '* User ID' (6045550001), '* Domain' (domainA.com), 'Password' (masked with dots), 'Display name' (Joseph Santos), and 'Authorization name'. The 'Domain Proxy' section has 'Register with domain and receive calls' checked, and 'Send outbound via' set to 'Domain'. The 'Dial plan' field contains the text '#1\a\a.T;match=1;prestrip=2;'. At the bottom are 'Cancel' and 'OK' buttons.

3. Complete the remaining tabs as specified by your service provider or to suit your setup. Settings that you may need to change immediately include:
 - General tab, Domain Proxy area.
 - Topology tab, if your computer is on a network and/or behind a firewall.For more information, see “Configuring X-Lite 4” on page 25.
4. When done, click OK; the account is enabled and registered; check the account list to make sure the account registers successfully.

Setting up for Voicemail

Your VoIP service provider may offer voicemail. If it does, then you can set up some voicemail features in X-Lite 4. See page 27.

Setting up a Contact List

Typically, you will want to create contacts in order to easily make calls and send IMs. See page 18.

2.3 Troubleshooting

X-Lite 4 includes tools for helping you troubleshoot problems. From the menu, choose Help > Troubleshooting.

- **Audio tab:** While you are on a phone call, you can test the quality of the audio. Note that to perform a valid test, you should be on an established call (not a call attempt).
- **Video tab:** You can verify that your camera is working.
- **Network tab:** You can verify that you are successfully connected to the network.
- **Devices tab:** You can verify that your microphone and speakers are working and can set the volume to a comfortable level without having to actually place a phone call.
- **Diagnostics tab:** If none of the other tabs help you solve your problem.


2.4 Checking for X-Lite 4 Updates

To check for updates to X-Lite 4, choose Help > Check for updates. The Auto Update window appears.

- If a new version of the software is available, you can download it from this window.
- If no newer version is available, this window informs you that your version is up to date.


3 Using X-Lite 4

3.1 The Onscreen Softphone



You can still receive calls when X-Lite is hidden or minimized.

The X-Lite 4 Menu




The menu contains the following items that are specific to X-Lite 4:

- X-Lite > Preferences. This menu item lets you configure X-Lite to work with your VoIP service and lets you change the way you work with X-Lite. See page 25.
- View. Change how X-Lite looks and show and hide specific modules.
- Contacts. Lets you work with contacts. Everything in this menu can also be performed directly in the contact list.
- Action. Lists the actions that you can perform, depending on the current “state” of X-Lite. For example, if a contact is selected, it lists all the actions that can be performed on that contact.
- Help. Provides access to various service-related features. See page 43.

Receiving an Online Status Request

When you start X-Lite, one of the first things you may see (if availability is enabled) is an Online Status Request dialog.




3.2 Placing a Call

You can contact someone using:

- A softphone address (for example, 6045550008@domainA.com or kperera@domainA.com).
- A traditional phone number, if supported by your VoIP service provider.

You can place one more call when another call is already in progress.



Place the call. See the table on the next page.


The outgoing call opens in its own call panel, below any other existing call panels. You will hear a ringing tone while X-Lite attempts to make a connection.

How	From the...	Description
Keying	Dialpad or computer keyboard	<ol style="list-style-type: none"> 1. Enter the number or address in the call entry field using the dialpad or the computer keyboard. If entering a softphone address, you can enter the entire address (6045550001@domainA.com or kperera@domainA.com) or just the name (6045550001 or kperera). As you type, a suggestion for completing the entry may appear. Choose the suggestion or keep typing. 2. Click the Call button or press Enter.
Drag-and-drop contact or previous call	Contacts or History tab	Drag an entry from the Contacts or History tab. (If the tab contains lots of contacts, first search or filter the list.)
Control-click a contact or previous call	Contacts or History tab	Control-click an entry from the Contacts or History tab and choose Call. (If the tab contains lots of entries, first search or filter the list.)
Redial	Redial button	<ul style="list-style-type: none"> • When the call entry field is empty, click the Call button. • Or click the arrow in the call entry field and select a recent call. An audio call is placed.
Dialing	Dialpad	<ol style="list-style-type: none"> 1. If the dialpad is not visible, click the Show/Hide dialpad button. 2. Click the numbers on the dialpad to enter the phone number. 3. Click the Call button or press Enter.

Placing another Call

To place a new call (without hanging up on the current call), simply place the call in the normal way. A second call panel opens below the current call. The first call is automatically put on hold.

Switch between the different calls by clicking Resume on the desired call panel. That call becomes the active call and all other calls are on hold.






Ending a Call

Click the red End call button on the Call panel (the call can be active or on hold). The call panel closes after a few seconds.

3.3 Handling an Incoming Call

X-Lite must be running to answer incoming calls. (If X-Lite is not running, incoming calls may be directed to voicemail; check with your VoIP service provider.)

As soon as an incoming call is received, a call panel appears, showing information about the call. The name and phone number of the person calling you is displayed. In addition, the Call Alert box appears, even if X-Lite is minimized.



Action	From the...	Description
Answer	Call panel or Call Alert box	Click Answer. If you are on another call, that first call is automatically put on hold. You are now talking to the new caller.
Decline	Call panel or Call Alert box	Click Decline. There will be a busy signal. The call may be directed to voicemail (if you have this service).
Video	Call panel or Alert box	The caller wants to include video. Click to answer a video call and start sending your video immediately.
Audio	Alert box	The caller wants to include video. Click to answer without video; if you want (and if you have a camera), you will be able to add video later.

3.4 Handling an Established Call


While the call is in progress you can:

- Control the audio: use the speakerphone, mute the call, control volume.
- Put the call on hold.



3.5 Handling Video Calls

Placing a Video Call



How	From the...	Description
Keying	Dialpad or computer keyboard	<ol style="list-style-type: none"> 1. Enter the number or address in the call entry field using the dialpad or the computer keyboard. If entering a softphone address, you can enter the entire address (6045550001@domainA.com or kperera@domainA.com) or just the name (6045550001 or kperera). As you type, a suggestion for completing the entry may appear. Choose the suggestion or keep typing. 2. Click the arrow beside the Call button and choose Video Call.
Control-click a contact or previous call	Contacts or History tab	<p>Control-click an entry from the Contacts or History tab and choose Video Call. (If the tab contains lots of entries, first search or filter the list.)</p>
Dialing	Dialpad	<ol style="list-style-type: none"> 1. If the dialpad is not visible, click the Show/Hide dialpad button. 2. Click the numbers on the dialpad to enter the phone number. 3. Click the arrow beside the Call button and choose Video Call.

Adding Video

If you have a camera, you can click Start Video to add video to an existing call. When you add video, the other party may (or may not) start sending their video to you.


Other Party Adds Video

If the other party starts their video, the video panel automatically opens and the video is played. You can start sending your own video, if desired (and assuming you have a camera) by clicking Start Video.

Pausing and Resuming Video


Click Stop Video or close the video window to pause sending your video.

Click Start Video to resume sending your video; the video window will open.



3.6 Voicemail

If your service includes voicemail and you have set up voicemail options (page 27), then when you have voicemail messages, a number appears beside the voicemail icon at the top of the phone. You can click the icon to automatically connect to voicemail and listen to your messages.




3.7 Instant Messaging

Instant messages are made using softphone addresses. Therefore, you can send or receive an instant message (IM) to:

- Any contact who has a softphone address.
- Any party who phoned you from a softphone address.
- Any party whom you phoned using a softphone address.

Sending an IM

1. There are several ways to select the person to send an IM to.


From the Contacts tab	Control-click on the contact and choose Send IM. The contact must have a softphone address.
An active phone call	The person in the active phone call. Click  on the call panel for this phone call.

The Instant Message window appears.

2. Type the message. Include emoticons and formatting, as desired.

To insert a return in the message, press Ctrl+Enter. (You can control the behavior of Enter and of Ctrl+Enter; see page 34)

3. Press Enter.




Receiving an IM

When an IM is received, the IM window pops up.

4 Using the Resources

4.1 Contacts Tab



The Contacts tab displays your contacts and lets you specify multiple contact methods for them, including:

- Softphone address
- Home phone number, business phone number, mobile phone number

You can identify one of these contacts as the primary contact method. When you double-click a contact, the action associated with that method is performed: typically either phone or IM.

Contacts are typically organized into groups. X-Lite includes built-in groups: “Family”, “Friends” and “Work”. You can add more groups, as desired.

Managing Contacts and Groups

Adding a Contact

Click , or control-click a group and choose Add Contact to Group. The Contact dialog appears. See the table.

Click to change the type of phone number:
“Softphone”, “Home”, “Work” and so on

Click + to add another phone number field
Click - to delete the selected entry

Table 1: Contact Fields

Field	Description
Group	Click to show the list of groups and check each group to add this contact to.
Contact name	Only the “Display as” name is required. This is the name that will appear in the call panel and the Call Alert when this person phones you.
Primary Call	If the contact has more than one number, select the primary number. This number will be used with the single-click calling and control-click calling.
Primary Presence	If the contact has more than one Softphone or IM address, choose one entry as the primary presence. The primary presence is used as follows: <ul style="list-style-type: none"> The presence icon on the contact list shows the online status for this address. The single-click and control-click actions for instant messaging use this address.
Softphone	Enter as many contact methods as you want. Use Softphone for someone who has a phone number that can also be used for presence and IM; you will be able to IM this person and view their presence. Otherwise, use Work, Home or another applicable method; X-Lite will not show a presence icon for this type of phone number.

Adding a Contact using an Existing Address

You can add a contact by capturing existing information. On the History tab, select an entry that is not a contact. Control-click and choose Add as Contact. The Contact dialog appears. Complete the dialog as desired and press OK.

If the contact method is Softphone, an online status request is sent to this person. See “Sharing Availability” on page 21.

Changing Contact Information

To change the information for a contact, control-click the contact and choose Edit Profile. The Contact dialog appears (see page 18).

Moving or Deleting a Contact

- To drag one or more contacts to a different group, select them and drag to the title bar of the new group.
- To delete one or more contacts, select them, control-click, and choose Delete or Delete Selected Items. The contacts are removed from this group. If a contact belongs to several groups, it is removed from all groups.

Adding, Deleting or Renaming Groups

Select any group, control-click, and choose the appropriate menu item.

Using Contacts

Phone the person

Control-click and choose Call, then click the desired number.

Send an IM


Control-click and choose Send IM. See page 15.

You can watch the contact's availability, if the contact has a softphone address

See Table 2 on page 23 for the meaning of the availability icons.

See "Sharing Online Status" on page 21 for information on obtaining availability information.

4.2 History Tab



Managing the Lists of Calls

You can control-click on an entry in a list to:


- Delete the call.
- Delete all entries in this list.
- Edit the profile if the entry is a contact.
- Add as contact. The Contact dialog appears. For more information on this dialog, see “Adding a Contact using an Existing Address” on page 18.

Phoning from History

You can control-click on an entry to place a call to this person, using the contact method that was used for this call.

4.3 Sharing Online Status

You can publish your online status to contacts who have softphone address, and you can set up X-Lite to view the online status of other contacts. Typical online statuses are available, on the phone, busy, and so on.



Sharing Availability

Watching Others' Availability

When you create a contact by entering details in the Contact, the contact is automatically set up so that you share availability. As soon as the person is set up in this way in your contact list, X-Lite sends them a notification request. The request asks that you be able to see that person's availability. If the person allows this request, then the icon beside their name (in your Contacts) becomes color coded, so you can determine their availability.

Allowing Other Parties to See your Availability (Publishing your Availability)


Continuing from above, when the other person allows the notification request, your name is added to their contact list. As soon as you are added to their list, a request is sent back to you requesting that they be able to see you. X-Lite accepts this request automatically, and the other person can now see your availability.

Receiving an Online Status Request

When someone who is not one of your contacts has you as a contact on their end, you receive an Online Status Request.

The request appears to you as an Online Status Request. You must respond to the request:

- Allow the request and create a new contact using this address. This option is selected for you if you do not currently have a contact with this SIP address.
- Allow the request and update the contact to allow the person to see your presence. This option is selected for you if you already have a contact with this SIP address but you were not previously sharing presence with this person.



Button	Result
Ignore	The other person will not be able to see your availability. The Online Status Request may appear again in this session or a future session
Allow	<p>The other person will be:</p> <ul style="list-style-type: none"> • Able to see your availability. • Added to your contacts. <p>Because you allow the request, you will no longer be bothered by requests from this person.</p> <p>In addition, this same request will automatically be sent from your X-Lite to the other person, so that you can see their availability.</p>

Setting your Online Status

Changing your Status

Click the down arrow beside the availability indicator on X-Lite, and select the desired availability. See Table 2, below. When your availability changes, the new availability is sent to your contacts.










Table 2: Availability Indicators

Indicator	Meaning for your Availability	Meaning for Others' Availability
 Available	<p>Either:</p> <ul style="list-style-type: none"> You have set your availability to this status. X-Lite has determined that you are logged on but not on the phone or idle. <p>When you have this availability, X-Lite will automatically detect when you are idle or on the phone, and change the availability to match.</p>	You can contact this person.
 Busy	You have set your availability to this status. X-Lite will never automatically switch you out of this status; you must switch yourself.	You can contact this person.
 Away	You have set your availability to this status. X-Lite will never automatically switch you out of this status; you must switch yourself.	You can contact this person.
 On the phone	<p>Either:</p> <ul style="list-style-type: none"> You have set your availability to this status. In this case, X-Lite will never automatically switch you out of this status; you must switch yourself. You started a phone call when your status was “Available”. When your call finishes, your status reverts to “Available”. 	You can contact this person.
 Idle	<p>You have not moved or clicked the mouse or pressed a keyboard key for the Idle period.</p> <p>As soon as you click the mouse or keyboard, your status changes to “Available”.</p>	You can contact this person.
 Offline	You have set your availability to this status. The other person sees you as offline, even though you are not actually offline. The other person cannot tell the difference between this status and you really being offline.	The contact is either not logged on or else is not set up for availability.
No icon	Not applicable	You are not watching the other person's availability.

Accounts – General

Account

Account name:

Protocol: SIP

Use for: Call IM/Presence

General Voicemail Topology Presence Transport Advanced

User Details

* User ID

* Domain

Password

Display name

Authorization name

Domain Proxy

Register with domain and receive calls

Send outbound via:

Domain

Proxy

Dial plan

Cancel OK

Fields with an asterisk are required

Table 3: Accounts – General

Field	Description
Account name	If desired, change the account name to something that is meaningful to you. For example, the name of the VoIP service provider.
Protocol	Read-only. Always specifies SIP.
Use for	Leave these fields checked.
User Details	
User ID	Provided by your VoIP service provider.
Domain	
Password	
Display name	This name is displayed in the X-Lite title bar. Other people will see you as this name.
Authorization name	May not be required. If it is required, it will be provided by your VoIP service provider.
Domain Proxy	
Register with domain and receive calls	Check this box if you want to register with your VoIP service provider, so that you can receive incoming calls. Typically, this field is checked. This field may be left unchecked when, for example, your level of service does not include the ability to receive incoming calls. In that case, turning this field on may cause registration to fail (when you close the Account Properties window), meaning that your X-Lite cannot register with your VoIP service provider.
Send outbound via	Choose the setting specified by your VoIP service provider: <ul style="list-style-type: none"> • Domain: If your VoIP service provider requires that traffic be directed to proxies that are discovered via the domain. • Proxy Address: If your VoIP service provider has an outbound proxy address and requires that you provide the address to X-Lite. For the address enter a domain name (for example, domain.com) or an IP address (for example, 123.456.789.012). If you are using X-Lite in a test lab, it is possible that neither of these settings is suitable; see page 33 for a third way to direct traffic.
Dial Plan	See page 47.

Accounts – Voicemail

These settings let you set up to interact with your VoIP service provider’s voicemail service. They also let you configure X-Lite to forward calls in several situations, independent of your VoIP service provider’s voicemail service.

Your service provider may provide the ability to set up for voicemail outside of X-Lite, for example, by phoning a softphone address and following the voice prompts, or by accessing a website.

Check with your service provider to determine if another setup mechanism is available. If so, check what the settings are in that setup, and make sure you enter compatible information in X-Lite.

In particular, if your service provider has a mechanism for call forwarding, find out if you should leave the Forwarding settings on this Voicemail tab blank.

Table 4: Accounts – Voicemail



Field	Description
Check for voicemail	<p>Set the checkbox in one of these ways:</p> <ul style="list-style-type: none"> • Check the box if X-Lite must subscribe to be notified when there is a voicemail for you. In other words, to configure for “subscribe for message waiting”. • Clear the checkbox if the service provider’s voicemail server sends notifications without X-Lite subscribing. In other words, to configure for “implicit subscription”. • Clear the checkbox if the service provider does not support voicemail. <p>Check with your VoIP service provider for the correct configuration.</p> <p>Voicemail is offered by your VoIP service provider; it is not part of X-Lite. Contact your service provider for information on using voicemail.</p>
Number to dial for checking voicemail	<p>Optional, but complete this field only if your VoIP service includes voicemail.</p> <ul style="list-style-type: none"> • Completing this field activates the  icon on the softphone. When you click the  icon, X-Lite will dial this number. You will be connected to your service provider’s voicemail and can listen to your messages. • If you leave this field empty, then this icon will not work; you will have to manually dial this number in order to connect to voicemail. <p>Enter the number or SIP address provided by your VoIP service provider.</p>

Table 4: Accounts – Voicemail

Field	Description
Number for sending calls to voicemail	<p>Complete only if your VoIP service includes voicemail. Optional, but you must complete it if you check “Send calls to voicemail if unanswered”.</p> <p>This is the number that incoming calls will be forwarded to if they are unanswered after the specified interval (below).</p> <p>If you leave this field empty, then X-Lite will never forward calls to your service provider’s voicemail. However, most VoIP service providers have their own mechanism for sending unanswered phone calls to voicemail. So leaving this field blank does not mean that forward-to-voicemail does not work.</p> <p>Enter the number provided by your VoIP service provider.</p>
Send calls to voicemail if unanswered	<p>Complete only if your VoIP service includes voicemail.</p> <p>To send to voicemail after the specified number of seconds.</p> <p>Your service provider may also provide a similar feature that is set up outside of X-Lite. If so, make sure you do not enter competing information in X-Lite and in the service provider’s user interface. For example, if you turn off this field, make sure the same feature at your service provider is also turned off. Otherwise, all your calls will continue to be forwarded.</p>

Accounts – Topology

Account

Account name: Account 1

Protocol: SIP

Use for: Call IM/Presence

General Voicemail **Topology** Presence Transport Advanced

Firewall Traversal

Firewall traversal method Auto-detect (ICE, recommended)
 Discover public IP address (STUN)
 Use media relay (TURN)
 None (use my local IP address)

To use domain server, leave Server Address blank

Server address

User name

Password

Range of ports used on local computer 0 - 0

Cancel OK

Table 5: Accounts – Topology

Field	Description
Firewall traversal method	<p>Leave the default. Or if you have problems making phone calls, contact your VoIP service provider for information on which of the other options might work:</p> <ul style="list-style-type: none"> • Auto detect using ICE: Automatically determine the contact address for signaling traffic. Advertise the local IP, public IP (discovered via STUN, if available), and media relay IP (discovered via TURN, if available), and use these to automatically determine the best route for media traffic during calls. • Discover public IP address: Advertise the public IP address (discovered via STUN) for the contact address for signaling traffic, and for the connection address for media traffic. • Use media relay (TURN): Advertise the public IP address (discovered via STUN) for the contact address for signaling traffic. Advertise the address of a media relay server (discovered via TURN) for the connection address for media traffic. • None: Advertise the local IP address only for both signaling and media traffic.
Server address	<ul style="list-style-type: none"> • Empty: Discover the address of the firewall traversal server (the STUN or TURN server), if available, using DNS SRV. • Specified: Use the firewall traversal server specified as either an IP address or a fully qualified hostname.
Range of ports	<p>The appropriate setting depends on your computer setup:</p> <ul style="list-style-type: none"> • Checked: If your computer is behind a restrictive firewall that only allows specific port ranges to be used. Enter the range of ports to use for your SIP account. (You must also open those ports on your firewall; refer to applicable firewall documentation for information.) • Unchecked: If your computer is not behind a restrictive firewall.

Accounts – Presence

Account

Account name:

Protocol: SIP

Use for: Call IM/Presence

General Voicemail Topology **Presence** Transport Advanced

Presence

Mode:

Poll time: seconds


Refresh interval: seconds

Presence allows your contacts to see your online availability and allows you to see the online availability of contacts. See “Sharing Online Status” on page 21.

Table 6: Accounts – Presence

Field	Description
Mode	Choose the setting specified by your VoIP service provider: <ul style="list-style-type: none"> • Disabled: Presence is not supported. • Peer-to-Peer.
Poll time	Enter the value specified by your VoIP service provider.
Refresh interval	Enter the value specified by your VoIP service provider.

Accounts – Transport



Contact your VoIP service provider to identify the types of transport that are supported. Then choose a supported transport:

- Automatic: X-Lite sets up the transport based on the capabilities of the network and the X-Lite computer. Choose this option if you do not care which transport is used.
- TCP
- UDP

Accounts – Advanced

Table 7: Accounts – Advanced

Field	Description
Register Settings	
Reregister every	The time interval between X-Lite's attempts to reregister in order to refresh the account registration with the VoIP service provider for this account. A value of zero means not to reregister after the initial registration. This value is placed in the "Expires" header field of the REGISTER message.
Minimum time	If the reregistration fails, X-Lite will wait this amount of time, then attempt to reregister. If the second attempt fails, X-Lite will wait twice this time and try again, then four times this time, and so on, until reregistration succeeds.
Maximum time	This is the maximum wait time between attempts to reregister. Once this maximum is reached, X-Lite will wait this time for all subsequent attempts. For example, the min. time is 20 secs, the maximum time is 120 secs. X-Lite will attempt to reregister as follows: <ul style="list-style-type: none"> • Wait 20 secs. • Attempt to connect. • If fail, wait 40 secs. • Attempt to connect. • If fail, wait 80 secs. • Attempt to connect. • If fail, wait 120 secs (the maximum) • Attempt to connect. • If fail, wait 120 secs, and so on.
Timers	
Enable session timers	A session timer is a mechanism to detect whether a call session is still active from the signaling point of view. When the timer expires, a refresh is sent from one party to the other. The timer is then reset. <ul style="list-style-type: none"> • Turn on to enable session timer. Enter a value in Default session time. • Turn off to disable session timer; refreshes will never be sent.
Default session time	

Table 7: Accounts – Advanced

Field	Description
Session timer preference	<p>This field specifies your preference for which party should send the refresh. The preference is not a guarantee that the refresh will be performed by the specified party. The choices are:</p> <ul style="list-style-type: none"> • None: No preference. • Local refreshes: Your computer sends. • Remote refreshes: The other party sends. • UAC refreshes: The user agent client (the party that initiated establishment of the communications) sends. • UAS refreshes: The user agent server (the other party) sends.
Send SIP keep-alives	Typically on, to instruct X-Lite to send SIP keep-alive messages in order to maintain a “pinhole” through your firewall for SIP messaging.
Use rport	Typically on.
Send outgoing request directly to target	<p>When checked, requests with a complete URI (user@ABC.com) go to ABC.com and the “Send outbound via” field on the General tab (page 26) is ignored.</p> <p>If you check this field, make sure you also set “Send outbound via” (on Accounts > Account) to “Domain”.</p> <p>Typically off. This field is intended for test labs and may cause problems in a NAT environment.</p>
Use old style hold	Check this box only if your VoIP service provider advises you to do so.

5.2 General Preferences


From the menu bar, choose X-Lite 4 > Preferences. The Preferences window appears. All the tabs on this window except for “Accounts” are preferences tabs. These tabs let you control the way that you work with X-Lite.

Preferences – Application



This panel lets you set your preferences for general GUI behavior.


Preferences – Alerts & Sounds



This panel lets you control the alert box and lets you assign sounds.

Enable Alert Displays

You can control whether the Call Alert box is displayed in different situations. You can also control how you are alerted to an incoming IM: either with a small IM Alert box or with the IM window itself.




Assigning Sounds

You can assign specific sounds to a variety of actions or “events”.

1. Select the Enable sounds check box and select the check boxes for each desired event, or clear the Enable sounds check box to disable all sounds.
2. If enabling sounds, you can change the sound for each event: select the individual event. The value in Sound preference will change. Select the desired sound.

You can import sounds; these will be added to the list of sounds you can choose from when assigning a sound to an event.

Preferences – Devices




X-Lite automatically detects devices at each startup, and selects the most appropriate device for each purpose. If you do not like this selection, you can override it on this panel.

If you override a selection, it will apply the next time you start X-Lite, unless the device is no longer available, in which case X-Lite will again select the device to use.

Field	Description
Headset Mode	
Microphone, Speaker	<p>Change these fields only if you want to override the devices that X-Lite automatically selected.</p> <p>In both these fields, select the headset you are using.</p> <p>The headset is the device that is usually used for audio out (the sound you hear) and audio in (recording your voice). The only situation in which the headset is not used is when the Speaker Phone button on the dialpad is pressed.</p> <p>Therefore, unless you will always be using X-Lite in speakerphone mode, you must make a selection here.</p> <p>Select the headset in both the Speaker device field and Microphone device field.</p>
Zero-touch device configuration	Typically, leave on. When device configuration is on, if you change your audio device, X-Lite will automatically detect the new device and start using it.
Test Devices	See “Troubleshooting” on page 43.
Speakerphone Mode	
Microphone	<p>Change this field only if you want to override the devices that X-Lite automatically selected.</p> <p>Make the appropriate choice:</p> <ul style="list-style-type: none"> • Select the device that you want to use for audio in (recording your voice) when the Speaker Phone button is pressed. <p>It can be any microphone: it does not have to be the microphone on the device you specified as the speaker device. For example, it can be the microphone on your camera.</p> <ul style="list-style-type: none"> • Select None if you do not have a speaker phone. The Speaker Phone button on the dialpad is disabled.
Speaker	<p>Change this field only if you want to override the devices that X-Lite automatically selected.</p> <p>Make the appropriate choice:</p> <ul style="list-style-type: none"> • Select the device that you want to use for audio out (the sound you hear) when the Speaker Phone button is pressed. Make sure you select a speaker device (not the headset). • Select None if you do not have a speaker phone. The Speaker Phone button on the dialpad is disabled.
Other Devices	
Ring on	<p>The device where you want to hear the phone ringing.</p> <p>Change this field only if you want to override the devices that X-Lite automatically selected.</p>
Volume	The volume of the ringer.
Camera	<p>This field appears only on versions of X-Lite that include video functionality.</p> <p>Change this field only if you want to override the devices that X-Lite automatically selected.</p> <p>Select the camera model.</p>
Resolution	<p>Leave at standard, or change the size as follows:</p> <ul style="list-style-type: none"> • Set it to high if you have a good camera and a computer with a fast CPU. You will know that you have set the size too large if: <ul style="list-style-type: none"> Your computer slows down (the video is using too much CPU) The video shows black areas or is slow or jerky. • Typically set it to low only in special situations, for example, when using wi-fi in a hotel. You will know that you have set the size too small if the video is fuzzy. <p>This field is identical to the Resolution field in Media Quality > Video Quality.</p>

Preferences – Network



Select the type of network connection for your computer.


The sliders move to show the bitrate that will be used for sending and receiving. These rates are typical rates for the selected configuration.

If you know that your computer and network can handle a faster sending speed, click Custom and move the slider. It is recommended that you not change the receiving speed.

- You will know that you have set the sending speed too high if the remote audio is garbled.
- You will know that you have set the sending speed too high if:
 - The remote video shows black areas or is slow or jerky.
 - The remote audio is garbled.
- You will know that you have set the sending speed too low if the audio is good but the video is of poor quality (grainy).

Preferences – Codecs

Audio Codecs



This panel shows all the codecs that are included in X-Lite. You can enable or disable codecs as desired.

With only one codec enabled, all calls made will use that codec. With more than one codec enabled, X-Lite automatically chooses the best codec based on the other party's capability, the available bandwidth, and network conditions.

You cannot change the properties of any codecs.

About Codecs

Audio codecs describe the format by which audio streams are compressed for transmission over networks. Codecs can be categorized as either narrowband or wideband:

- Narrowband codecs work with low bandwidth such as a dialup internet connection. These codecs have a sampling rate of 8 kHz.
- Wideband codecs work with high bandwidths and result in better audio quality. However, they do not work with PSTN. These codecs have a sampling rate of 16 kHz.

Supported Codecs

Codec	Narrowband	Wideband
Broadvoice-32		✓
Broadvoice-32 FEC		✓
DVI4	✓	
DVI4 Wideband		✓
G.711aLaw *	✓	
G.711uLaw *	✓	
GSM	✓	
iLBC	✓	
L16 PCM Wideband	✓	
Speex	✓	
Speex FEC	✓	

Codec	Narrowband	Wideband
Speex Wideband		✓
Speex Wideband FEC		✓
* Generally, at least one of these codecs must be enabled in order to place a PSTN (land line) call.		

Video Codecs

Video codecs describe the format by which video streams are compressed for transmission over networks. Some codecs require less bandwidth than others, but may result in lower video quality.

You can enable or disable codecs as desired. You may decide to disable a codec even though your VoIP service provider supports it.


With only one codec enabled, all calls made will use that particular compression format. With more than one codec enabled, X-Lite automatically chooses the best codec based on the other party's capability, the available bandwidth, and network conditions.

You cannot change the properties of any codecs.

Supported Codecs


- H.263
- H.263+1998

Preferences – Media Quality



Field	Description
Audio Quality	
Reduce echo	Turning this feature on improves sound quality. This feature is typically on.
Reduce background noise	Automatically attempts to remove background noise. Typically on for the speakerphone.
Automatic gain control	This feature is typically on.
Preserve bandwidth	When this feature is on, X-Lite stops sending audio when you are not talking. When this feature is off, X-Lite always sends audio, which uses more bandwidth but may result in better call quality. Typically off. However, if you are using a slow (dial-up or ISDN) connection, you may want to turn it on.
Video Quality	
Resolution	Leave at standard, or change the size as follows: <ul style="list-style-type: none"> Set it to high if you have a good camera and a computer with a fast CPU. You will know that you have set the size too large if: <ul style="list-style-type: none"> Your computer slows down (the video is using too much CPU) The video shows black areas or is slow or jerky. Typically set it to low only in special situations, for example, when using wi-fi in a hotel. You will know that you have set the size too small if the video is fuzzy. This field is identical to the Resolution field in Devices > Other Devices.

Preferences – Advanced




Field	Description
DTMF	You may need to change the DTMF configuration if you cannot interact with interactive voice response systems (auto attendants, voice-activated menus, and so on). Contact your VoIP service provider for the correct setting.
RTP	This timer controls how calls are disconnected when X-Lite determines that there is a problem with the call and the other party has probably disappeared (assuming that you have not yourself detected the problem and hung up manually). Typically, the timer is enabled. It is recommended that you not disable it. You can change the length of the timer, but do not set it to less than 30 seconds.

A Troubleshooting

Choose Help > Troubleshooting to display the Troubleshooting window.


Testing Audio Quality

While you are on a phone call, you can test the quality of the audio. Note that to perform a valid test, you should be on an established call (not a call attempt).




Testing Video Quality

While you are on a phone call, you can test the quality of the video. Note that to perform a valid test, you should be on an established call (not a call attempt).



Testing the Network Connection

You can verify that you are successfully connected to the network.




Testing Devices

You can verify that your microphone and speakers are working and can set the volume to a comfortable level without having to actually place a phone call.




Diagnostics

Only use this panel if instructed to do so by your support representative at your VoIP service provider.



To start logging X-Lite activity and send a logging report to customer support:

1. Click Start Logging. The first Diagnostics Logging window appears.
2. Select the problem you are experiencing and click Start Logging.
3. On the second Diagnostics Logging screen, click Finish. Logging will start.
4. Perform the actions you want to capture; for example, attempt to make a phone call.
5. When done, display the first Diagnostics Logging window again and click Send Report. A window opens; select the report and click Open. When the report is successfully sent, a confirmation message appears on the first Diagnostics window.
6. Click Stop Logging. Close the Troubleshooting window.



B Dial Plan

You can create a dial plan to modify the the call input (what you type, select or drag onto the call entry field) to ensure that the call gets placed successfully. Modifying the input is useful when using numbers from a contact, which may include symbols such as the + symbol.

Do You Need to Read this Information?

You do not have to read this dial plan information if the default dial plan behavior (below) is acceptable.

If you need to modify the input (for example, to prefix the number with “9”), then you must create a dial plan.

The Default Dial Plan

The default dial plan is:

```
#n\a\a.T;match=1;prestrip=2;
```

where #n is the account prefix; in other words #1 for the first account and so on.

X-Lite supports only one SIP account, so there is no point in including the #1 when you place a call. However, if you are used to eyeBeam, you may be used to entering #1. This dial plan supports that habit: the dialplan removes the #1 and then places the call on the SIP account.

B.1 Dial Plan Activity

When you make a call, X-Lite takes the phone number (the input) and performs the following:

- **Cleanup.** This step is not part of the dial plan: it is always performed even when there is no dial plan. Input is cleaned up by removing spaces, dashes, open brackets, and close brackets. Cleanup allows X-Lite to support calls placed using contacts from a contact list, including Microsoft® Outlook®.
- **Matching.** X-Lite compares the input to the patterns in the dial plan. If a match is found, the transformation associated with the pattern is performed.
- **Transformation.** If a match is found between the input and a pattern, that pattern’s transformation (if any) is performed.
- **Place Call.** Then the call is placed using the transformed input.

B.2 Dial Plan Syntax

The dial plan has the following syntax:

```
pattern[ |pattern];match=1;<transformation>=<value>;[match=2;
<transformation>=<value>;]
```

Where:

- Items in [] are optional.

- **Pattern:** the pattern that will be matched. One or more patterns. Each pattern is separated by a | pipe. The pipe is optional after the last pattern. Each pattern is implicitly numbered, starting from 1.
- **Match; Transformation:** A pair that identifies the pattern number to compare with the input, and the transformation to perform on the input when a match is obtained. The transformation is optional (meaning that if there is no transformation for a pattern, then the input that matches this pattern is not transformed). One or more pairs.
“match=” is a literal. “n” identifies the pattern. “transformation=” is replaced by a keyword, see below.
“value” is replaced by a value.

Spaces are allowed only in the <value> items.

Remember that dial plans are applied after the input has been cleaned up!

Example

```
\a\a.T|xxxxxxxxxx;match=1;prestrip=2;match=2;pre=8;
```

where:

- \a\a.T is the first pattern.
- xxxxxxxxxxxx; is the second pattern.
- match=1;prestrip=2; is the first match-transformation pair.
- match=2;pre=8; is the second match-transformation pair.

Pattern

Valid Content

The content for a pattern follows the digit map rules of RFC 2705, supplemented by the rules for regular expressions. Where there is an overlap between the digit map and regular expression rules, the digit map rules apply. For this reason, there are some special cases, included in the table below.

The following table describes the most common elements. All regular expression elements are supported.

Element	Origin	Description
	Regular expression rules	Pipe character, used to separate patterns.
0 1 2 3 4 5 6 7 8 9	Literals	Literal digits, used as is.
# * a to z	Literals	Literal characters, used as is. Special cases: <ul style="list-style-type: none"> • The literal x character is represented by \x. • The literal t character is represented by \t.
x	Digit map rules	Wildcard for any single digit, 0 to 9.
\a	Regular expression rules	Wildcard for any single alphanumeric character.
[digit-digit]	Regular expression rules	A digit within the specified range.
[character-character]	Regular expression rules	A character within the specified range.
[digit1, digit2, digit3]	Regular expression rules	One of the characters in the collection.

Element	Origin	Description
.	Digit map rules	Repeat the last element 0 or more times. For example, xxxx. means repeat the last x 0 or more times, which means this pattern matches three or more digits (not four or more digits)! Use of this element results in a pattern with “minimum requirements”.
T	Digit map rules	<p>A timeout period will take place before automatic dialing starts.</p> <p>The T timer forces X-Lite to wait after a match is made. This timer should always be included in these situations:</p> <ul style="list-style-type: none"> Any pattern that uses the . (dot). For example, if the pattern is xxxx. then adding a timer lets you type three or more digits. If there is no timer, then as soon as you type three digits, X-Lite makes the match as soon as you type three digits. Any dial plan that has two patterns that are similar in elements but different in length. For example, if one pattern is xxx and the other pattern is xxxxxxx, then adding the timer lets you continue typing past three digits, in order to get a match on the second pattern. <p>In this situation, the T timer should be included in the shorter pattern.</p>

Transformation Keywords

Keyword	Description
prestrip	Strip the first n characters from the input before placing the call.
poststrip	Remove n number of characters from the end of the input before placing the call.
pre	Add the specified prefix to the input before placing the call.
post	Attach the specified postfix to the input before placing the call.
replace	Replaces the input with the specified string before placing the call.

Order of Transformations

These transformations are always performed in the following order (the order in which the transformations are entered in the dial plan is not significant):

prestrip > poststrip > pre > post > replace

B.3 How the Input Is Processed

Comparing Input to the Dial Plan Patterns

The input is compared to the dial plan. Keep in mind that the input being compared is different depending on whether the input is dragged/selected or typed:

- If the input is dragged or selected, then the entire input is compared to each pattern.
- If you are typing the input, then the digits are compared one by one as they are entered. Each time a new digit is entered, the comparison starts over again.

Results of the Comparison

X-Lite finds a match according to the following rules.

Type of Match	Result If User Presses Enter or Call	Result if User Stops typing
The input matches the pattern and the pattern does not include the T timer	The transformation is performed. X-Lite attempts the call.	Nothing happens even after the T timer has expired.
The input matches the pattern and the pattern includes the T timer	The transformation is performed. X-Lite attempts the call.	The transformation is performed. X-Lite 4 attempts the call.
The input does not match the pattern	No transformation is performed. X-Lite attempts the call.	Nothing happens even after the T timer has expired.

B.4 Examples

Example 1

```
\a\a.T|xxxxxxx.T;match=2;pre="9"
```

This simple example shows how to differentiate between a PSTN number and a softphone address, and how to add a “9” dialing prefix only to the PSTN number.

Example 2

```
3xxT|1xxxxxxxxxxx|[2-9]xxxxxxxxxx|+x.T;match=2;pre="9";  
match=3;pre="91";match=4;prestrip=1;pre="9011"
```

3xxT	The first pattern is any three-digit number beginning with 3. No transformation. The assumption is that this is an internal extension. The timer forces X-Lite to wait after detecting a three-digit number beginning with 3, in case you are actually dialing a local call starting with 3.
1xxxxxxxxxxx	The second pattern is any eleven-digit number beginning with 1. Prefix with 9 and dial as is. The assumption is that this is a long-distance PSTN call within North America (within North America, all long-distance calls start with 1).
[2-9]xxxxxxxxxx	The third pattern is any ten-digit number beginning with a number other than 1. The assumption is that this is a local PSTN call within a ten-digit dialing zone.
+x.T;	The fourth pattern is a number of any length that begins with +, to indicate an international PSTN call from North America. Delete the +, prefix with 9011 (011 is the number to access an international line from North America).
match=2;pre="9";	For the second pattern, prefix 9 to access an outside line.
match=3;pre="91";	For the third pattern, prefix 9 and 1 to access an outside line and enter the long-distance code.
match=4;prestrip=1; pre="9011"	For the fourth pattern, remove the + and prefix 9011 to access an outside line and enter the international code.

C Location of Data Files

Data files are saved in the standard location for application data. This location is typically:

<user directory>/Library/Preferences/CounterPath Corporation/X-Lite 4

D Glossary

AEC	Acoustic echo cancellation. Processing of the audio signal to reduce the echo effect that can arise with a speakerphone or that can arise if the sound from the speakerphone or headphone leaks into the microphone.
AGC	Automatic gain control. Processing of the audio to adjust the microphone volume level so that the other party does not hear the distortion that might be caused by too high a microphone input or too low volume (due to too low input level).
Broadband	Broad or wide bandwidth. In data transmission, the wider the band, the more data it is possible to transmit in a given time span. A cable, DSL and ADSL connection to the network provide broadband for data transmission. A dialup or ISDN connection typically provide a narrow bandwidth for data transmission.
Codec	The format by which audio streams are compressed for transmission over networks.
Default account	The SIP account that will be used when placing an outgoing call, if X-Lite does not determine that another account should be used. X-Lite uses the dial plan to determine the account to use.
Dial plan	The rules that X-Lite follows in order to interpret the softphone address or phone number that the user has entered and to modify the number or address, as required, to ensure that the call will be placed successfully.
DTMF	Dual-tone multi frequency. DTMF is the system that is used in interactive voice-response menu systems such as the menu system for accessing voicemail messages. The DTMF system allows the user to interact with the menu by pressing keys on a dialpad or keyboard.
IM	Instant Messaging. A technology that lets users send text message and files for near instantaneous delivery and display on each others' computers.
IP	Internet Protocol. A data-oriented protocol used for communicating data across a network. IP is the most common protocol used on the internet.
IP address	A unique number that devices use in order to identify and communicate with each other on a computer network using the IP standard.
Media	In a VoIP phone call, the audio portion of the information in a call. Compare to "Signaling".
MOV	The Mac QuickTime multimedia container format. MOV files contain audio data in a standard container that allows simultaneous playback.
MWI	Message Waiting Indicator. An indicator that there is a voicemail message for the owner of an account.
Narrowband	In data transmission, the wider the band, the more data it is possible to transmit in a given time span. A cable, DSL and ADSL connection to the network provide broadband for data transmission. A dialup or ISDN connection typically provide a narrow bandwidth for data transmission.
Presence	An instant messaging feature that allows users to share information about their availability, mood, location and so on.
Proxy	See SIP account.
PSTN	Public Switch Telephone Network. The traditional land-line phone network.
RFC	Request for Comment. A document that describes an aspect of an internet technology. An RFC may be a proposed, draft or full internet standard.
RTP	Real-time Transport Protocol. A protocol for delivering the media portion of a data transmission over an IP network. SRTP is another media protocol.

Signaling	In a VoIP phone call, the information in a call that deals with establishing and controlling the connection, and managing the network. The non-signaling portion of the call is the Media.
SIMPLE protocol	Session Initiation Protocol for Instant Messaging and Presence Leveraging Extensions. The instant messaging (IM) protocol followed by X-Lite. It encapsulate the rules for exchanging instant messages.
SIP	Session Initiation Protocol. The signaling protocol followed by X-Lite for handling phone calls.
SIP account	An account that provides the user the ability to make VoIP phone calls. The account encapsulates the rules and functions the user can access.
softphone address	The address used to connect to a SIP endpoint. In other words, the “phone number” used in a VoIP phone call. For example, sip:joseph@domainA.com.
SRTP	Secure Real-time Transport Protocol. A protocol for delivering the media portion of a data transmission over an IP network. SRTP is a secure protocol, which means that the media is encrypted. RTP is another media protocol.
TCP	Transmission Control Protocol. A transport protocol for delivering data over an IP network. Other transport protocols are TLS and UDP.
UDP	User Datagram Protocol. A transport protocol for delivering data over an IP network. Another transport protocol is TCP.
URI	Uniform Resource Identifier. A name or address that identifies a location on the world wide web. A softphone address is a type of URI.
URL	Uniform Resource Locator. A URI that both identifies a name or address and indicates how to locate it.
USB device	Universal Serial Bus device. A device that follows a specific communications standard. A headset may be a “USB type” of headset.
VAD	Voice Activity Detection. A technology that detects if audio is a human voice or background noise. X-Lite includes a feature (Preserve bandwidth on the Network panel of the Preferences window) that controls whether audio is transmitted when VAD determines that no one is actually speaking.
VoIP	Voice over Internet Protocol. A variation of IP used for sending voice data over the internet, in other words, used for making phone calls over the internet.
WAV	Or WAVE. A file format standard for storing audio on PCs.

